Subprograms

In Text: Chapter 8

Outline

- Definitions
- Referencing environments
- Parameter passing modes and mechanisms
- Independent & separate compilation
- Advanced subprogram issues

Characteristics of Subprograms

- **Fundamental characteristics:**
  - A subprogram has a single entry point
  - The caller is suspended during execution of the called subprogram
  - Control always returns to the caller when the called subprogram's execution terminates

Basic Definitions

- A subprogram definition is a description of the actions of the subprogram abstraction
- A subprogram call is an explicit request that the subprogram be executed
- A subprogram header is the first line of the definition, including the name, the kind of subprogram, and the formal parameters
- The parameter profile of a subprogram is the number, order, and types of its parameters
- The protocol of a subprogram is its parameter profile plus, if it is a function, its return type

More Definitions

- A subprogram declaration provides the protocol, but not the body, of the subprogram
- A formal parameter is a dummy variable listed in the subprogram header and used in the subprogram
- An actual parameter represents a value or address used in the subprogram call statement

Actual/Formal Param Correspondence

- Two basic choices:
  - Positional
  - Keyword

```
Sort (List => A, Length => N);
```

- For named association:
  - Advantage: order is irrelevant
  - Disadvantage: user must know the formal parameter's names

Default Parameter Values

- **Example, in Ada:**

```
procedure sort (list   : List_Type;
                length : Integer := 100);
  ...
sort (list => A);
```

Two Types of Subprograms

- Procedures provide user-defined statements
- Functions provide user-defined operators

Design Issues for Subprograms

- What parameter passing methods are provided?
- Are parameter types checked?
- Are local variables static or dynamic?
- What is the referencing environment of a passed subprogram?
- Are parameter types in passed subprograms checked?
- Can subprogram definitions be nested?
- Can subprograms be overloaded?
- Are subprograms allowed to be generic?
- Is separate/independent compilation supported?

Local Referencing Environments

- If local variables are stack-dynamic:
  - Advantages:
    - Support for recursion
    - Storage for locals is shared among some subprograms
  - Disadvantages:
    - Allocation/deallocation time
    - Indirect addressing
    - Subprograms cannot be history sensitive
- Static locals are the opposite

Local Variables in Example PLs

- FORTRAN 77 and 90—most are static, but can have either (SAVE forces static)
- C—both; default is stack dynamic, but variables declared to be static are
- Pascal, Modula-2, and Ada—dynamic only

Parameters and Parameter Passing

- Semantic Models: in mode, out mode, inout mode
- Conceptual Models of Transfer:
  - Physically move a value
  - Move an access path
- Implementation Models:
  - Pass-by-value
  - Pass-by-result
  - Pass-by-value-result
  - Pass-by-reference
  - Pass-by-name

Pass-By-Value

- in mode
- Either by physical move or access path
- Disadvantages of access path method:
  - Must write-protect in the called subprogram
  - Accesses cost more (indirect addressing)
- Disadvantages of physical move:
  - Requires more storage
  - Cost of the moves

Pass-By-Result

- out mode
- Local's value is passed back to the caller
- Physical move is usually used
- Disadvantages:
  - If value is moved, time and space
  - In both cases, order dependence may be a problem

```
procedure sub1(y: int, z: int);
    ...
sub1(x, x);
```

- Value of x in the caller depends on order of assignments at the return

Pass-By-Value-Result

- inout mode
- Physical move, both ways
- Also called pass-by-copy
- Disadvantages:
  - Those of pass-by-result
  - Those of pass-by-value

Pass-By-Reference

- inout mode
- Pass an access path
- Also called pass-by-sharing
- Advantage: passing process is efficient
- Disadvantages:
  - Slower accesses
  - Can allow aliasing:
    - Actual parameter collisions: sub1(x, x);
    - Array element collisions: sub1(a[i], a[j]); /* if i = j */
    - Collision between formals and globals
- Root cause of all of these is: The called subprogram is provided wider access to nonlocals than is necessary
- Pass-by-value-result does not allow these aliases (but has other problems!)

Pass-By-Name

- multiple modes
- By textual substitution
- Formals are bound to an access method at the time of the call, but actual binding to a value or address takes place at the time of a reference or assignment
- Purpose: flexibility of late binding
- Resulting semantics:
  - If actual is a scalar variable, it is pass-by-reference
  - If actual is a constant expression, it is pass-by-value
  - If actual is an array element, it is like nothing else
  - If actual is an expression with a reference to a variable that is also accessible in the program, it is also like nothing else

Pass-By-Name Example 1

```
procedure sub1(x: int; y: int);
begin
   x := 1;
   y := 2;
   x := 2;
   y := 3;
end;

sub1(i, a[i]);
```

Pass-By-Name Example 2

- Assume k is a global variable

```
procedure sub1(x: int; y: int; z: int);
begin
      k := 1;
   y := x;
   k := 5;
   z := x;
end;

sub1(k+1, j, i);
```

Disadvantages of Pass-By-Name

- Very inefficient references
- Too tricky; hard to read and understand

Param Passing: Language Examples

- FORTRAN
  - Before 77, pass-by-reference
  - 77—scalar variables are often passed by value-result
- ALGOL 60
  - Pass-by-name is default; pass-by-value is optional
- ALGOL W: Pass-by-value-result
- C: Pass-by-value
- Pascal and Modula-2: Default is pass-by-value; pass-by-reference is optional

Param Passing: PL Examples (cont.)

- C++: Like C, but also allows reference type parameters, which provide the efficiency of pass-by-reference with in-mode semantics
- Ada
  - All three semantic modes are available
  - If out, it cannot be referenced
  - If in, it cannot be assigned
- Java
  - Like C++, except only references

Type Checking Parameters

- Now considered very important for reliability
- FORTRAN 77 and original C: none
- Pascal, Modula-2, FORTRAN 90, Java, and Ada: it is always required
- ANSI C and C++: choice is made by the user

Implementing Parameter Passing

- ALGOL 60 and most of its descendants use the run-time stack
- Value—copy it to the stack; references are indirect to the stack
- Result—same
- Reference—regardless of form, put the address in the stack
- Name:
  - Run-time resident code segments or subprograms evaluate the address of the parameter
  - Called for each reference to the formal
  - These are called thunks
  - Very expensive, compared to reference or value-result

Ada Param Passing Implementations

- Simple variables are passed by copy (value-result)
- Structured types can be either by copy or reference
- This can be a problem, because
  - Aliasing differences (reference allows aliases, but value-result does not)
  - Procedure termination by error can produce different actual parameter results
- Programs with such errors are “erroneous”

Multidimensional Arrays as Params

- If a multidimensional array is passed to a subprogram and the subprogram is separately compiled, the compiler needs to know the declared size of that array to build the storage mapping function
- C and C++
  - Programmer is required to include the declared sizes of all but the first subscript in the actual parameter
  - This disallows writing flexible subprograms
  - Solution: pass a pointer to the array and the sizes of the dimensions as other parameters; the user must include the storage mapping function, which is in terms of the size parameters (See example, p. 351)

More Array Passing Designs

- Pascal
  - Not a problem (declared size is part of the array's type)
- Ada
  - Constrained arrays—like Pascal
  - Unconstrained arrays—declared size is part of the object declaration (See book example p. 351)
- Pre-90 FORTRAN
  - Formal parameter declarations for arrays can include passed parameters
- SUBPROGRAM SUB(MATRIX, ROWS, COLS, RESULT)
  INTEGER ROWS, COLS
  REAL MATRIX (ROWS, COLS), RESULT
  ...
  END

Design Considerations for Parameter Passing

- Efficiency
- One-way or two-way
- These two are in conflict with one another!
- Good programming => limited access to variables, which means one-way whenever possible
- Efficiency => pass by reference is fastest way to pass structures of significant size
- Also, functions should not allow reference parameters

Subprograms As Parameters: Issues

- Are parameter types checked?
  - Early Pascal and FORTRAN 77 do not
  - Later versions of Pascal, Modula–2, and FORTRAN 90 do
  - Ada does not allow subprogram parameters
  - C and C++ – pass pointers to functions; parameters can be type checked

Subprogs as Params: Issues (cont.)

- What is the correct referencing environment for a subprogram that was sent as a parameter?
  - Possibilities:
    - It is that of the subprogram that called it (shallow binding)
    - It is that of the subprogram that declared it (deep binding)
    - It is that of the subprogram that passed it (ad hoc binding, never been used)
  - For static-scoped languages, deep binding is most natural
  - For dynamic-scoped languages, shallow binding is most natural

Overloading

- An overloaded subprogram is one that has the same name as another subprogram in the same referencing environment
- C++ and Ada have overloaded subprograms built-in, and users can write their own overloaded subprograms

Generic Subprograms

- A generic or polymorphic subprogram is one that takes parameters of different types on different activations
- Overloaded subprograms provide ad hoc polymorphism
- A subprogram that takes a generic parameter that is used in a type expression that describes the type of the parameters of the subprogram provides parametric polymorphism
- See Ada generic and C++ template examples in text

Independent and Separate Comp.

- Independent compilation is compilation of some of the units of a program separately from the rest of the program, without the benefit of interface information
- Separate compilation is compilation of some of the units of a program separately from the rest of the program, using interface information to check the correctness of the interface between the two parts

Language Examples:

- FORTRAN II to FORTRAN 77: independent
- FORTRAN 90, Ada, Modula-2, C++: separate
- Pascal: allows neither

Functions

Design Issues:

- **Are side effects allowed?**
  - **Two-way parameters (Ada does not allow)**
  - **Nonlocal reference (all allow)**
- **What types of return values are allowed?**
  - **FORTRAN, Pascal, Modula-2: only simple types**
  - **C: any type except functions and arrays**
  - **Ada: any type (but subprograms are not types)**
  - **C++ and Java: like C, but also allow classes to be returned**

Accessing Nonlocal Environments

- The nonlocal variables of a subprogram are those that are visible but not declared in the subprogram
- Global variables are those that may be visible in all of the subprograms of a program

Methods for Accessing Nonlocals

- FORTRAN COMMON
  - The only way in pre-90 FORTRANs to access nonlocal variables
  - Can be used to share data or share storage
- Static scoping—discussed in Chapter 4
- External declarations: C
  - Subprograms are not nested
  - Globals are created by external declarations (they are simply defined outside any function)
  - Access is by either implicit or explicit declaration
  - Declarations (not definitions) give types to externally defined variables (and say they are defined elsewhere)
- External modules: Ada and Modula-2: Sec Ch. 10
- Dynamic Scope: discussed in Ch. 4

User-Defined Overloaded Operators

- Nearly all programming languages have overloaded operators
- Users can further overload operators in C++ and Ada (not carried over into Java)
- Ada Example (where Vector_Type is an array of Integers):

```
function "*"(a, b : in Vector_Type) return Integer is
   sum : Integer := 0;
begin
   for index in a'range loop
      sum := sum + a(index) * b(index);
   end loop;
   return sum;
end "*";
```

- Are user-defined overloaded operators good or bad?

Coroutines

- A coroutine is a subprogram that has multiple entries and controls them itself
- Also called symmetric control
- A coroutine call is named a resume
- The first resume of a coroutine is to its beginning, but subsequent calls enter at the point just after the last executed statement in the coroutine
- Typically, coroutines repeatedly resume each other, possibly forever
- Coroutines provide quasiconcurrent execution of program units (the coroutines)
- Their execution is interleaved, but not overlapped