

Implementing Subprograms

In Text: Chapter 10

Outline

- General semantics of calls and returns
- Implementing "simple" subroutines
- Call Stack
- Implementing subroutines with stack-dynamic local variables
- Nested programs

N. Meng, S. Arthur

2

General Semantics of Calls and Returns

- The subroutine call and return operations are together called **subroutine linkage**
- The implementation of subroutines must be based on the semantics of the subroutine linkage

N. Meng, S. Arthur

3

Semantics of a subroutine call

- Save the execution status of the current program unit
- Pass the parameters
- Pass the return address to the callee
- Transfer control to the callee

N. Meng, S. Arthur

4

Semantics of a subroutine return

- If there are pass-by-value-result or out-mode parameters, the current values of those parameters are moved to the corresponding actual parameters
- Move the return value to a place accessible to the caller
- The execution status of the caller is restored
- Control is transferred back to the caller

N. Meng, S. Arthur

5

Storage of Information

- The call and return actions require storage for the following:
 - Status information about the caller
 - Parameters
 - Return address
 - Return value for functions
 - Local variables

N. Meng, S. Arthur

6

Implementing "simple" subroutines

- **Simple subroutines** are those that cannot be nested and all local variables are static
- A simple subroutine consists of two parts: code and data
 - Code: constant (instruction space)
 - Data: can change when the subroutine is executed (data space)
 - Both parts have fixed sizes

N. Meng, S. Arthur 7

Activation Record

- The format, or layout, of the data part is called an **activation record**, because the data is relevant to an activation, or execution, of the subroutine
- The form of an activation record is static
- An **activation record instance** is a concrete example of an activation record, corresponding to one execution

N. Meng, S. Arthur 8

An activation record for simple subroutine

Local variables
Parameters
Return address

- Since the activation record instance of a "simple" subprogram with fixed size, it can be statically allocated
- Actually, it could be attached to the code part of the subprogram

N. Meng, S. Arthur 9

The code and activation records of a program with simple subroutines

- Four program units—MAIN, A, B, and C
- MAIN calls A, B, and C
- Originally, all four programs may be compiled at different times individually
- When each program is compiled, its machine code, along with a list of references to external subprograms are written to a file

N. Meng, S. Arthur 10

How is the code linked?

- A linker is called for MAIN to create an executable program
 - Linker is part of the OS
 - Linker is also called *loader*, *linker/loader*, or *link editor*
 - It finds and loads all referenced subroutines, including code and activation records, into memory
 - It sets the target addresses of calls to those subroutines' entry addresses

N. Meng, S. Arthur 11

Assumptions so far...

- All local variables are statically allocated
- No function recursion
- No value returned from any function

N. Meng, S. Arthur 12

Call Stack

- **Call stack** is a stack data structure that stores information about the active subroutines of a program
- Also known as **execution stack, control stack, runtime-stack, or machine stack**
- Large array which typically grows downwards in memory towards lower addresses, shrinks upwards

N. Meng, S. Arthur 13

Call Stack

- Push(r1):


```
stack_pointer--;
M[stack_pointer] = r1;
```
- r1 = Pop();


```
r1 = M[stack_pointer];
stack_pointer++;
```

N. Meng, S. Arthur 14

Call Stack

- When a function is invoked, its activation record is created dynamically and pushed onto the stack
- When a function returns, its activation record is popped from the stack
- The activation record on stack is also called **stack frame**
- **Stack pointer(sp)**: points to the frame top
- **Frame pointer(fp)**: points to the frame base

N. Meng, S. Arthur 15

Implementing subroutines with stack-dynamic local variables

- One important advantage of stack-dynamic local variables is support for recursion
- The implementation requires more complex activation records
 - The compiler must generate code to cause the implicit allocation and deallocation of local variables

N. Meng, S. Arthur 16

More complex activation records

Local variables
Parameters
Dynamic link
Return address

↑ Stack top

- Since the return address, dynamic link, and parameters are placed in the activation record instance by the caller, these entries must appear first
- Local variables are allocated and possibly initialized in the callee, so they appear last

N. Meng, S. Arthur 17

Dynamic Link (control link) = previous sp

- Used in the destruction of the current activation record instance when the procedure completes its execution
- To restore the sp in previous frame (caller)
- The collection of dynamic links in the stack at a given time is called the **dynamic chain**, or **call chain**, which represents the dynamic history of how execution got to its current position

N. Meng, S. Arthur 18

Why do we need dynamic links?

Temporaries
Local variables
Parameters
Dynamic link
Return address

↑ Stack top

- The dynamic link is required in some cases, because there are other allocations from the stack by a subroutine beyond its activation record, such as temporaries
- Even though the activation record size is known, we cannot simply subtract the size from the stack pointer to remove the activation record
- Access nonlocal variables in dynamic scoped languages

N. Meng, S. Arthur 19


An Example without Recursion

```

void fun1(float r) {
  int s, t;
  ... ←-----1
  fun2(s);
}
void fun2(int x) {
  int y;
  ... ←-----2
  fun3(y);
}
...
void fun3(int q) {
  ... ←-----3
}
void main() {
  float p;
  ...
  fun1(p);
}
    
```

- Call sequence: main → fun1 → fun2 → fun3
- What is the stack content at points labeled as 1, 2, and 3?

N. Meng, S. Arthur 20



Local Variable Allocation

- Local scalar variables are bound to storage within an activation record instance
- Local variables that are structures are sometimes allocated elsewhere, and only leave their descriptors and a pointer to the storage as part of the activation record

N. Meng, S. Arthur 22

An Example

```

void sub(float total, int part) {
  int list[5];
  float sum;
  ...
}
    
```

Local	sum
Local	list[4]
Local	list[3]
Local	list[2]
Local	list[1]
Local	list[0]
Parameter	part
Parameter	total
Dynamic link	
Return address	

N. Meng, S. Arthur 23

Recursion

- Function recursion means that a function can eventually call itself
- Recursion adds the possibility of multiple simultaneous activations of a subroutine at a given time, with at least one call from outside the subroutine, and one or more recursive calls
- Each activation requires its own activation record

N. Meng, S. Arthur 24

An Example

```
int factorial(int n) {
  if (n <= 1)
    return 1;
  else return (n * factorial(n - 1));
}
void main() {
  int value;
  value = factorial(3);
}
```

How does the stack change?

N. Meng, S. Arthur

25

Implementing nested subroutines

- Some static-scoped languages use stack-dynamic local variables and allow subroutines to be nested
 - FORTRAN 95, Ada, Python, and JavaScript
- Challenge
 - How to access nonlocal variables?

N. Meng, S. Arthur

26

Two-step access process

- Find the activation record instance on the stack where the variable was allocated
 - more challenging and more difficult
- Use the **local_offset** of the variable to access it
 - local_offset describes the offset from the beginning/bottom of an activation record

N. Meng, S. Arthur

27

Key Observations

- In a given subroutine, only variables that are declared in static ancestor scopes are visible and can be accessed
- Activation record instances of all static ancestors are always on the stack when variables in them are referenced by a nested subroutine: A subroutine is callable only when all its static ancestors are active

N. Meng, S. Arthur

28

Finding Activation Record Instance

- Static chaining
 - A new pointer, **static link (static scope pointer or access link)**, is used to point to the bottom of an activation record instance of the static parent
 - The pointer is used for access to nonlocal variables
 - Typically, the static link appears below parameters in an activation record

N. Meng, S. Arthur

29

Finding Activation Record Instance (cont'd)

- A static chain is a chain of static links that connect the activation record instances of all static ancestors for an executing subroutine
- This chain can be used to implement nonlocal variable access

Local variables
Parameters
Dynamic link
Static link
Return address

N. Meng, S. Arthur

30

Finding Activation Record Instance (cont'd)

- With static links, finding the correct activation record instance is simple
 - Search the static chain until a static ancestor is found to contain the variable
- However, the implementation can be even simpler
 - Compiler identifies both nonlocal references, and the length of static chain to follow to reach the correct record

N. Meng, S. Arthur

31

Finding Activation Record Instance (cont'd)

- **static_depth** is an integer associated with a static scope that indicates how deeply it is nested in the outermost scope
- The difference between the static_depth of a nonlocal reference and the static_depth of the variable definition is called **nesting_depth**, or **chain_depth**, of the reference
- Each reference is represented with an ordered integer pair (chain_offset, local_offset)

N. Meng, S. Arthur

32

An Ada Example

```

procedure Main_2 is
  X : Integer;
  procedure Bigsub is
    A, B, C : Integer;
    procedure Sub1 is
      A, D : Integer;
      begin -- of Sub1
        A := B + C; <-----1
      end; -- of Sub1
    procedure Sub2(X : Integer) is
      B, E : Integer;
      procedure Sub3 is
        C, E : Integer;
        begin -- of Sub3
          Sub1;
          E := B + A; <-----2
        end; -- of Sub3
      begin -- of Sub2
        Sub3;
        A := D + E; <-----3
      end; -- of Sub2
    begin -- of Bigsub
      Sub2(7);
    end; -- of Bigsub
  begin
    Bigsub;
  end;

```

Main_2 calls Bigsub
Bigsub calls Sub2
Sub2 calls Sub3
Sub3 calls Sub1

What is the static depth for each procedure?
What is the representation of A at points 1, 2, and 3?

N. Meng, S. Arthur


33

Stack Contents

```

procedure Main_2 is
  X : Integer;
  procedure Bigsub is
    A, B, C : Integer;
    procedure Sub1 is
      A, D : Integer;
      begin -- of Sub1
        A := B + C; <-----1
      end; -- of Sub1
    procedure Sub2(X : Integer) is
      B, E : Integer;
      procedure Sub3 is
        C, E : Integer;
        begin -- of Sub3
          Sub1;
          E := B + A; <-----2
        end; -- of Sub3
      begin -- of Sub2
        Sub3;
        A := D + E; <-----3
      end; -- of Sub2
    begin -- of Bigsub
      Sub2(7);
    end; -- of Bigsub
  begin
    Bigsub;
  end;
end; of Main_2

```



N. Meng, S. Arthur

Solutions

- What is the static depth for each procedure?
 - Main_2: 0, Bigsub: 1, Sub1: 2, Sub2: 2, Sub3: 3
- What is the representation of A at points 1, 2, and 3?
 - 1: A<0, 3>, 2: A<2, 3>, 3: A<1, 3>

N. Meng, S. Arthur

35