Subprograms

In Text: Chapter 9

Outline

- · Definitions
- Design issues for subroutines
- Parameter passing modes and mechanisms
- · Advanced subroutine issues

N. Meng, S. Arthur

Subroutine

- A sequence of program instructions that perform a specific task, packaged as a unit
- The unit can be used in programs whenever the particular task should be performed

N. Meng, S. Arthur

Subroutine

- Subroutines are the fundamental building blocks of programs
- They may be defined within programs, or separately in libraries that can be used by multiple programs
- In different programming languages, a subroutine may be called a procedure, a routine, a method, or a subprogram

N. Meng, S. Arthur

Characteristics of Subroutines/ Subprograms

- Each subroutine has a single entry
- The caller is suspended during the execution of the callee subroutine
- Control always returns to the caller when callee subroutine's execution terminates

N. Meng, S. Arthur

Parameters

- A subroutine may be written to expect one or more data values from the calling program
- The expected values are called parameters or formal parameters
- The actual values provided by the calling program are called arguments or actual parameters

Actual/Formal Parameter Correspondence

- Two options
 - Positional parameters
 - In nearly all programming languages, the binding is done by position
 - E.g., the first actual parameter is bound to the first formal parameter
 - Keyword parameters
 - · Each formal parameter and the corresponding actual parameter are specified together
 - E.g., Sort (List => A, Length => N)

N. Meng, S. Arthur

Keyword Parameters

- Advantages
 - Order is irrelevant
 - When a parameter list is long, developers won't make the mistake of wrongly ordered parameters
- Disadvantages
 - Users must know and specify the names of formal parameters

N. Meng, S. Arthur

Default Parameter

- A parameter that has a default value provided to it
- If the user does not supply a value for this parameter, the default value will be used
- If the user does supply a value for the default parameter, the user-specified value is used

N. Meng, S. Arthur

An Example in Ada

procedure sort (list : List_Type; length : Integer := 100);

sort (list => A);

Design issues for subroutines

- · What parameter passing methods are provided?
- Are parameter types checked?
- What is the referencing environment of a passed subroutine?
- Can subroutine definitions be nested?
- · Can subroutines be overloaded?
- · Are subroutines allowed to be generic?
- Is separate/independent compilation supported?


Parameter-Passing Methods

- · Ways in which parameters are transmitted to and/or from callee subroutines
 - Semantic models
 - Implementation models

Semantic Models

- Formal parameters are characterized by one of three distinct semantic models
 - In mode: They can receive data from the corresponding actual parameters
 - Out mode: they can transmit data to the actual parameters
 - Inout mode: they can do both

N. Meng, S. Arthur



An Example

```
public int[] merge(int[] arr1, int[] arr2) {
  int[] arr = new int[arr1.length + arr2.length];
  for (int i = 0; i < arr2.length; i++) {
        arr[i] = arr1[i];
        arr2[i] = arr1[i] + arr2[i];
        arr[i + arr1.length] = arr2[i];
    }
  return arr;
}</pre>
```

Which parameter is in mode, out mode, or inout mode?

N. Meng, S. Arthur

Implementation Models

- A variety of models have been developed by language designers to guide the implementation of the three basic parameter transmission modes
 - Pass-by-value
 - Pass-by-result
 - Pass-by-value-result
 - Pass-by-reference
 - Pass-by-name

N. Meng, S. Arthur

Pass-by-Value

- The value of the actual parameter is used to initialize the corresponding formal parameter, which then acts as a local variable in the subprogram
- Implement in-mode semantics
- Implemented by copy

ng, S. Arthur

Pros and Cons

- Pros
 - Fast for scalars, in both linkage cost and access time
 - No side effects to the parameters
- · Cons
 - Require extra storage for copying data
 - The storage and copy operations can be costly if the parameter is large, such as an array with many elements

Pass-by-Result

- · No value is transmitted to a subroutine
- The corresponding formal parameter acts as a local variable, whose value is transmitted back to the caller's actual parameter

```
- E.g., void Fixer(out int x, out int y) {
    x = 17;
    y = 35;
}
```

• Implement out-mode parameters

ng. S. Arthur

Pros and Cons

- Pros
 - Same as pass-by-value
- · Cons
 - The same cons of pass-by-value
 - Parameter collision
 - E.g., Fixer(x, x), what will happen?
 - If the assignment statements inside Fixer() can be reordered, what will happen?

N. Meng, S. Arthur

20

Pass-by-Value-Result

- A combination of pass-by-value and passby-result, also called pass-by-copy
- Implement inout-mode parameters
- Two steps
 - The value of the actual parameter is used to initialize the corresponding formal parameter
 - The formal parameter acts as a local variable, and at subroutine termination, its value is transmitted back to the actual parameter

hur

Pros and Cons

- Pros
 - Same as pass-by-reference, which is to be discussed next
- Cons
 - Same as pass-by-result

N. Meng, S. Arthur

22

Pass-by-Reference

- A second implementation model for inout-mode parameters
- Rather than copying data values back and forth, it shares an access path, usually an address, with the caller
 - E.g., void fun(int &first, int &second)

z, S. Arthur

Pros and Cons

- Pros
 - Passing process is efficient in terms of time and space
- Cons
 - Access to the formal parameters is slower than pass-by-value parameters due to indirect access via reference
 - Side effects to parameters
 - Aliases can be created

An Example: pass-by-value-result vs. pass-by-reference

```
program foo;
var x: int:
    procedure p(y: int);
    begin
       y := y + 1;
       y := y * x;
                                      pass-by-value-result pass-by-reference
    end
begin
   x := 2;
   p(x);
                       (after y:= y + 1)
   print(x);
                        (at p's return)
```

N. Meng, S. Arthur

Aliases can be created due to passby-reference

- · Given void fun(int &first, int &second),
 - Actual parameter collisions
 - E.g., fun(total, total) makes first and second to be aliases
 - Array element collisions
 - E.g., fun(list[i], list[j]) can cause first and second to be aliases if i == j
 - Collisions between formals and globals
 - E.g., int* global; void main() { ... sub(global); ... } void sub(int* param) { ... }
 - Inside sub, param and global are aliases

Pass-by-Name

- Implement an inout-mode parameter transition method
- The body of a function is interpreted at call time after textually substituting the actual parameters into the function body
- The evaluation method is similar to C preprocessor macros

An Example in Algol

```
procedure double(x);
  real x;
begin
  x := x * 2;
end;
```

Therefore, double(C[j]) is interpreted as C[j] = C[j] * 2

N. Meng, S. Arthur

Another Example

```
· Assume k is a global variable,
procedure sub2(x: int; y: int; z: int);
begin
```

k := 1;

y := x; k := 5;

 How is the function call sub2(k+1, j, i) interpreted?

N. Meng, S. Arthur

Disadvantages of Pass-by-Name

- Very inefficient references
- · Too tricky; hard to read and understand

Implementing Parameter-Passing Methods

- Most languages use the runtime stack to pass parameters
 - Pass-by-value
 - · Values are copied into stack locations
 - Pass-by-result
 - Values assigned to the actual parameters are placed in the stack
 - Pass-by-value-result
 - A combination of pass-by-value and pass-by-result
 - Pass-by-reference
 - · Parameter addresses are put in the stack


iur

An Example

- Function header: void sub (int a, int b, int c, int d)
 - -a: pass by value
 - -b: pass by result
 - -c: pass by value-result
 - d: pass by reference
- Function call: main() calls sub(w, x, y, z)

N. Meng, S. Arthur

32



Design Considerations for Parameter Passing

- Efficiency
- Whether one-way or two-way data transfer is needed

N. Meng, S. Arthur

One Software Engineering Principle

- Access by subroutine code to data outside the subroutine should be minimized
 - In-mode parameters are used whenever no data is returned to the caller
 - Out-mode parameters are used when no data is transferred to the callee but the subroutine must transmit data back to the caller
 - Inout-mode parameters are used only when data must move in both directions between the caller and callee

N. Meng, S. Arthur

A practical consideration in conflict with the principle

 Pass-by-reference is the fastest way to pass structures of significant size

I. Meng, S. Arthur

vrtnur 3