

Chapter 9

High-level Synchronization

Introduction to Concurrency

■ Concurrency

- Execute two or more pieces of code "at the same time"

■ Why ?

- No choice:
 - Geographically distributed data
 - Interoperability of different machines
 - A piece of code must "serve" many other client processes
 - To achieve reliability
- By choice:
 - To achieve speedup
 - Sometimes makes programming easier (e.g., UNIX pipes)

CS 3204

Possibilities for Concurrency

Architecture:	Program Style:
Uniprocessor with: <ul style="list-style-type: none">- I/O channel- I/O processor- DMA	Multiprogramming, multiple process system programs
Multiprocessor	Parallel programming
Network of processors	Distributed Programs

CS 3204

Examples of Concurrency in Uniprocessors

Example 1: Unix pipes

Motivations:

- fast to write code
- fast to execute

Example 2: Buffering

Motivation:

- required when two asynchronous processes must communicate

Example 3: Client/Server model

Motivation:

- geographically distributed computing

CS 3204

Operating System issues to Support Concurrency

■ Synchronization

- What primitives should OS provide ?

■ Communication

- What primitives should the OS provide to the interface communication protocol ?

■ Hardware Support

- Needed to implement OS primitives

CS 3204

Operating System issues to Support Concurrency...

■ Remote execution

- What primitives should OS provide ?
 - Remote Procedure Call (RPC)
 - Remote Command Shell

■ Sharing address space

- Makes programming easier

■ Light-weight threads

- Can a process creation be as cheap as a procedure call ?

CS 3204

Definitions

- **Concurrent** process execution can be:
 - interleaved, or
 - physically simultaneous
- **Interleaved**
 - Multi-programming on uniprocessor
- **Physically simultaneous**
 - Uni- or multi-programming on multiprocessor

CS 3204

Definitions...

- **Process, thread, or task**
 - Scheduleable unit of computation
- **Granularity**
 - Process "size" or computation to
 - Communication ratio
 - Too small: excessive overhead
 - Too large: less concurrency

CS 3204

Precedence Graph


Consider writing a program as a set of tasks.

Precedence graph:

specifies execution ordering among tasks

```

S1:  A := X + Y
S2:  B := Z + 1
S3:  C := A - B
S4:  W := C + 1
    
```



Parallelizing compilers for computers with vector processors build dependency graphs.

CS 3204

Cyclic Precedence Graph

What does the following graph represent ?

S2 must be performed before S3 begins

AND

S3 must be performed before S2 begins

Precedence Graphs must be **ACYCLIC**



CS 3204

Concurrency Conditions

Let S_i denote a statement.

Read set of S_i :

$R(S_i) = \{a_1, a_2, \dots, a_n\}$

Set of all variables referenced in S_i

Write set of S_i :

$W(S_i) = \{b_1, b_2, \dots, b_m\}$,

Set of all variables changed by S_i

CS 3204

Concurrency Conditions...

$C := A - B$

$R(C := A - B) = \{A, B\}$

$W(C := A - B) = \{C\}$

$\text{cin} \gg A$

$R(\text{cin} \gg A) = \{\}$

$W(\text{cin} \gg A) = \{A\}$

CS 3204

Bernstein's Conditions

The following conditions must hold for two statements S1 and S2 to execute concurrently with valid results:

- 1) $R(S1) \cap W(S2) = \{\}$
- 2) $W(S1) \cap R(S2) = \{\}$
- 3) $W(S1) \cap W(S2) = \{\}$

These are called the **Bernstein Conditions**.

CS 3204

Structured Parallel Constructs

PARBEGIN / PAREND

PARBEGIN Sequential execution splits off into several concurrent sequences

PAREND Parallel computations merge

```
PARBEGIN
  Statement 1;
  Statement 2;
  ...
  Statement N;
PAREND;
```

```
PARBEGIN
  Q := C mod 25;
Begin
  N := N - 1;
  T := N / 5;
End;
Proc1 ( X, Y );
PAREND;
```

CS 3204


Parbegin / Parend Examples

```
Begin
  PARBEGIN
    A := X + Y;
    B := Z + 1;
  PAREND;
  C := A - B;
  W := C + 1;
End;
```

```
Begin
  S1;
  PARBEGIN
    S3;
    BEGIN
      S2;
      S4;
    PARBEGIN
      S5;
      S6;
    PAREND;
  End;
  S7;
PAREND;
End;
```

CS 3204

Parbegin / Parend Examples



CS 3204

Synchronization with Monitors

Monitors

- P & V are primitive operations
- Semaphore solutions are difficult to accurately express for complex synchronization problems
- Need a High-Level solution: Monitors
- A Monitor is a collection of procedures and shared data
- Mutual Exclusion is enforced at the monitor boundary by the monitor itself
- Data may be global to all procedures in the monitor or local to a particular procedure
- No access of data is allowed from outside the monitor

CS 3204

Condition Variables

- Within the monitor, Condition Variables are declared
- A queue is associated with each condition variable
- Only two operations are allowed on a condition variable:


X.wait	The procedure performing the wait is put on the queue associated with x
X.signal	If queue is non-empty: resume <i>some</i> process at the point it was made to wait

- Note: V operations on a semaphore are "remembered," but if there are no waiting processes, the signal has no effect
- OS scheduler decides which of several waiting monitor calls to unlock upon signal

CS 3204

Monitor...



- Queue to enter monitor via calls to procedures
- Queues within the monitors via condition variables
- ADTs and condition variables only accessible via monitor procedure calls



CS 3204

Monitors...

Monitors contain procedures that control access to a < CS >, but not the < CS > code itself.



CS 3204

N-Process Critical Section: Monitor Solution

```

Monitor NCS {
    OK: condition
    Busy: boolean <-- FALSE

    Request() {
        if (Busy) OK.wait;
        Busy = TRUE;
    }

    Release() {
        Busy = FALSE;
        OK.signal;
    }
}

Procedure P {
    NCS.Request();
    <CS>;
    NCS.Release();
}

main() {
    parbegin P;P;P;P; parend }
    
```

CS 3204

Shared Variable Monitor

```

monitor sharedBalance {
    int balance;

    public:
        Procedure credit(int amount)
        { balance = balance + amount;}

        Procedure debit(int amount)
        { balance = balance - amount;}
    }
    
```

CS 3204

Reader & Writer Schema

```

reader() {
    while(true) {
        ...
        startRead();
        <read the resource>
        finishRead();
        ...
    }
}

writer() {
    while(true) {
        ...
        startWrite();
        <write resource>
        finishWrite();
        ...
    }
}

fork(reader, 0);
fork(reader, 0);
fork(writer, 0);
    
```


CS 3204

Reader & Writers Problem: The solution

```
monitor reader_writer_2{
    int numberOfReaders = 0;
    boolean busy = false;
    condition okToRead, okToWrite;
public:
    startRead(){
        if(busy || okToWrite.queue) okToRead.wait;
        numberOfReaders = numberOfReaders+1;
        okToRead.signal;
    }
    finishRead(){
        numberOfReaders = numberOfReaders-1;
        if(numberOfReaders == 0) okToWrite.signal;
    }
    startWrite(){
        if(busy || numberOfReaders != 0) okToWrite.wait;
        busy = true;
    }
    finishWrite(){
        busy = false;
        if(okToWrite.queue) okToWrite.signal;
        else okToRead.signal;
    }
}
```

CS 3204

Dining Philosophers' Problem



```
while(TRUE) {
    think();
    eat();
}
```

CS 3204

Dining Philosophers' Problem: The solution

```
enum status {eating, hungry, thinking};
monitor diningPhilosophers{
    status state[N]; condition self[N]; int i;
    // This procedure can only be called from within the monitor
    test(int i) {
        if((state[i-1 MOD N] != eating) && (state[i] == hungry)
            && (state[i+1 MOD N] != eating)) {
            state[i] = eating;
            self[i].signal;
        }
    }
public:
    pickUpForks(){
        state[i] = hungry;
        test(i);
        if(state[i] != eating) self[i].wait;
    }
    putDownForks(){
        state[i] = thinking;
        test(i-1 MOD N); test(i+1 MOD N);
    }
    diningPhilosophers() { // Monitor initialization code
        for(int i=0; i<N; i++) state[i] = thinking;
    }
}
```

CS 3204

Monitor implementation of a ring buffer

```
monitor ringBufferMonitor;
var ringBuffer: array[0..slots-1] of stuff;
slotInUse: 0..slots;
nextSlotToFill: 0..slots-1;
nextSlotToEmpty: 0..slots-1;
ringBufferHasData, ringBufferHasSpace: condition;
procedure fillASlot(slotData: stuff);
begin
    if(slotInUse = slots) then wait(ringBufferHasSpace);
    ringBuffer[nextSlotToFill] := slotData;
    slotInUse := slotInUse + 1;
    nextSlotToFill := (nextSlotToFill+1) MOD slots;
    signal(ringBufferHasData);
end;
```

CS 3204

Monitor implementation of a buffer...

```
procedure emptyASlot(var slotData: stuff);
begin
    if(slotInUse = 0) then wait(ringBufferHasData);
    slotData := ringBuffer[nextSlotToEmpty];
    slotInUse := slotInUse - 1;
    nextSlotToEmpty := (nextSlotToEmpty-1) MOD slots;
    signal(ringBufferSpace);
end;
begin
    slotInUse := 0;
    nextSlotToFill := 0;
    nextSlotToEmpty := 0;
end.
```

CS 3204